

静态nat与标准acl的混合使用思科认证 PDF转换可能丢失图片或格式，建议阅读原文

https://www.100test.com/kao_ti2020/616/2021_2022_E9_9D_99_E6_80_81nat_E4_c101_616912.htm 静态nat与标准acl 的混合使用
gt.、 将pc0和pc1得ip转换为环回地址。 gt.、 阻止1.1.1.2 的通信 Router 1配置： Router >en Router#conf t Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int f 0/0 Router(config-if)#ip add 1.1.1.1 255.0.0.0
Router(config-if)#no shut %LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
Router(config-if)#int f0/1 Router(config-if)#ip add 2.2.2.1 255.0.0.0
Router(config-if)#no shutdown %LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up Router(config-if)#exit
Router(config)# %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up Router(config)#int loopback 0 %LINK-5-CHANGED: Interface Loopback0, changed state to up %LINEPROTO-5-UPDOWN: Line protocol on Interface Loopback0, changed state to up Router(config-if)#ip add 4.4.4.1 255.0.0.0 Router(config-if)#no shut Router(config-if)#exit
Router(config)#router rip Router(config-router)#network 1.0.0.0
Router(config-router)#network 2.0.0.0
Router(config-router)#network 4.0.0.0 Router(config-router)#end
%SYS-5-CONFIG_I: Configured from console by console
Router#show ip rou Router#show ip route Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP D - EIGRP, EX -

EIGRP external, O - OSPF, IA - OSPF inter area N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2 E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area * - candidate default, U - per-user static route, o - ODR P - periodic downloaded static route Gateway of last resort is not set C 1.0.0.0/8 is directly connected, FastEthernet0/0 C 2.0.0.0/8 is directly connected, FastEthernet0/1 R 3.0.0.0/8 [120/1] via 2.2.2.2, 00:00:11, FastEthernet0/1 C 4.0.0.0/8 is directly connected, Loopback0 Router#configure terminal Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#ip nat inside source s Router(config)#ip nat inside source static 1.1.1.2 4.4.4.2 Router(config)#ip nat inside source static 1.1.1.3 4.4.4.3 Router(config)#interface fastEthernet 0/0 Router(config-if)#ip nat in Router(config-if)#ip nat inside Router(config-if)#no shut Router(config-if)#no shutdown Router(config-if)#int f0/1 Router(config-if)#ip nat outside Router(config-if)#end %SYS-5-CONFIG_I: Configured from console by console Router#show ip nat ? statistics Translation statistics translations Translation entries Router#show ip nat tr Router#show ip nat translations Pro Inside global Inside local Outside local Outside global --- 4.4.4.2 1.1.1.2 --- --- --- 4.4.4.3 1.1.1.3 --- --- Router#ping 3.3.3.2 Type escape sequence to abort. Sending 5, 100-byte ICMP Echos to 3.3.3.2, timeout is 2 seconds: !!!!! 100Test 下载频道开通，各类考试题目直接下载。详细请访问 www.100test.com