

Cisco路由配置语句汇总 PDF转换可能丢失图片或格式，建议阅读原文

https://www.100test.com/kao_ti2020/142/2021_2022_Cisco_E8_B7_AF_E7_94_c101_142315.htm 启动接口，分配IP地址： router> router> enable router# router# configure terminal router(config)# router(config)# interface Type Port router(config-if)# no shutdown router(config-if)# ip address IP-Address Subnet-Mask
router(config-if)# ^ z 配置RIP路由协议：30秒更新一次
router(config)# router rip router(config-if)# network Network-Number router(config-if)# ^ z 配置IGRP路由协议：90秒更新一次 router(config)# router igrp AS-Number
router(config-if)# network Network-Number router(config-if)# ^ z 配置Novell IPX路由协议：Novell RIP 60秒更新一次
router(config)# ipx routing [node address] router(config)# ipx maximum-paths Paths router(config)# interface Type Port
router(config-if)# ipx network Network-Number [encapsulation encapsulation-type] [secondary] router(config-if)# ^ z 配置DDR
： router(config)# dialer-list Group-Number protocol Protocol-Type permit [list ACL-Number] router(config)# interface bri 0 router(config-if)# dialer-group Group-Number
router(config-if)# dialer map Protocol-Type Next-Hop-Address name Hostname Telephone-Number router(config-if)# ^ z 配置ISDN : router(config)# isdn swith-type Swith-Type
router(config-if)# ^ z 配置Frame Relay : router(config-if)# encapsulation frame-relay [cisco | ietf] router(config-if)# frame-relay lmi-type [ansi | cisco | q933a] router(config-if)#

bandwidth kilobits router(config-if)# frame-relay invers-arp [Protocol] [dlci] router(config)# frame-relay Protocol Protocol-Address DLCI [Broadcast] [ietf | cisco] [payload-compress | packet-by-packet] router(config-if)# keepalive Number router(config-if)# frame-relay local-dlci Number router(config-if)# interface Type Port.Subinterface-Number [multipoint | point-to-point] router(config-subif)# ip unnumbered Interface router(config-subif)# frame-relay local-dlci Number router(config-if)# ^ z 100Test 下载频道开通，各类考试题目直接下载。 详细请访问 www.100test.com