

Cisco网络教材：6520路由器参数设置 PDF转换可能丢失图片或格式，建议阅读原文

[https://www.100test.com/kao\\_ti2020/142/2021\\_2022\\_Cisco\\_E7\\_BD\\_91\\_E7\\_BB\\_c101\\_142758.htm](https://www.100test.com/kao_ti2020/142/2021_2022_Cisco_E7_BD_91_E7_BB_c101_142758.htm) Cisco网络教材：6520路由器参数设置

以下为主要参数设置：一、1、NODE 6 ( CONFIGURE ) , 1 ( NODE ) NODE NAME : JH10XX98/ NODE ADDRESS : 85023153/ ROUTE SELECTION TABLE SIZE : 32/

MNEMONIC TABLE SIZE : 32/ 2、X.25 PORT 6 , 2 ( PORT ) PORT NUMBER : 1/ [1]\*PORT TYPE : X25/ [1]

CONNECTION TYPE : SIMP/ [1] PORT CONTROL : NONE/ [1] CLOCK SPEED : 64000/ [1] LINK ADDRESS : DTE/

[1]\*NUMBER OF PVC CHANNELS : 0/ [1]\*STARTING PVC CHANNEL NUMBER : 1/ [1]\*NUMBER OF SVC CHANNELS

: 128/ [1]P PACKET SIZE : 1024 [1]X.25 OPTIONS : CAUSE/ 3、ROUTE SELECTION TABLE 6.3 ( CONFIGURE NETWORK SERVICES ) .1 ( ROUTE SELECTION TABLE CONFIGURE )

ENTRY NUMBER : 1/3 [3]ADDRESS : \*\*\*\*\*/ [3]#1 DESTINATION : X25-1/ [3]#1 PRIORITY : 1/ 4、MNEMONIC TABLE 6.3.3 ( MNEMONIC TABLE ) ENTRY NUMBER : 1/

[1]MNEMONIC NAME : U6000/ [1] CALL PARAMETERS : 2001005303/ ENTRY NUMBER : 2/ [2]MNEMONIC NAME : JH60XX98/ [2] CALL PARAMETERS : 2011134294/ ENTRY NUMBER : 3/ [3]MNEMONIC NAME : JH10CA98/ [3] CALL PARAMETERS : 8502510394/ ENTRY NUMBER : 4/

[4]MNEMONIC NAME : JH9999/ [4] CALL PARAMETERS : 2001225394/ ENTRY NUMBER : 5/ [5]MNEMONIC NAME

: JH10DA98/ [5] CALL PARAMETERS : 8521710594/ ENTRY NUMBER : 6/ [6] MNEMONIC NAME : JH10AA98/ [6] CALL PARAMETERS : 8521710494/ ENTRY NUMBER : 7/ [7] MNEMONIC NAME : JH10DB98/ [7] CALL PARAMETERS : 8502910994/ ENTRY NUMBER : 8/ [8] MNEMONIC NAME : JH10DC98/ [8] CALL PARAMETERS : 8502410294/ ENTRY NUMBER : 9/ [9] MNEMONIC NAME : JH10DD98/ [9] CALL PARAMETERS : 8501811094/ ENTRY NUMBER : 10/ [10] MNEMONIC NAME : JH10DF98/ [10] CALL PARAMETERS : 8502710294/ ENTRY NUMBER : 11/ [11] MNEMONIC NAME : JH10EA98/ [11] CALL PARAMETERS : 8521210294/ ENTRY NUMBER : 12/ [12] MNEMONIC NAME : JH10EB98/ [12] CALL PARAMETERS : 8521610194/ ENTRY NUMBER : 13/ [13] MNEMONIC NAME : JH10EC98/ [13] CALL PARAMETERS : 8521410294/ ENTRY NUMBER : 14/ [14] MNEMONIC NAME : JH10ED98/ [14] CALL PARAMETERS : 8521510194/ ENTRY NUMBER : 15/ [15] MNEMONIC NAME : JH10EE98/ [15] CALL PARAMETERS : 8521310294/ ENTRY NUMBER : 16/ [16] MNEMONIC NAME : JH10DE98/ [16] CALL PARAMETERS : 8502415194/ ENTRY NUMBER : 17/ [17] MNEMONIC NAME : JH10BX98/ [17] CALL PARAMETERS : 850121100594/ 5、 X25 ROUTE TABLE 6.3.1 ( ROUTE SELECTION TABLE ) ENTRY NUMBER : 1/ [1] ADDRESS : 8502315394/ [1] #1 DESTINATION : LCON/ 二、 1、 CONFIGURE INTERFACE STATES 6.18 ( CONFIG ROUTE ) .1 ( CONFIG

INTERFACE STATES ) #INTERFACE #1 STATE : ENABLED  
#INTERFACE #5 STATE : ENABLED #INTERFACE #6 STATE  
: ENABLED #INTERFACE #7 STATE : ENABLED 2、 6.18.4  
( CONFIGURE IP ) .1 ( PARAMETERS ) \*MAXIMUM  
NUMBER OF IP INTERFACES : 36/ \*INTERNAL IP ADDRESS :  
( BLANK ) / \*INTERNAL NET MASK : 255.255.255.0/ \*ACCESS  
CONTROL : ENABLE/ \*RIP ENABLE : DISABLE/ 3  
、 INTERFACES 6.18.4.2 ( INTERFACES ) ENTRY NUMBER  
: 1/ [1]\*INTERFACE NUMBER : 1/ [1]\*IP ADDRESS  
: 20.59.28.98/ [1]\*IP ADDRESS MASK : 255.255.255.0/ ENTRY  
NUMBER : 2 / [2]\*INTERFACE NUMBER : 5 / [2]\*IP  
ADDRESS : 20.1.254.65/ [2]\*IP ADDRESS MASK : 255.255.0.0/  
ENTRY NUMBER : 3 / [3]\*INTERFACE NUMBER : 6 / [3]\*IP  
ADDRESS : 20.58.254.1/ [3]\*IP ADDRESS MASK : 255.255.0.0/  
ENTRY NUMBER : 4 / [4]\*INTERFACE NUMBER : 7 / [4]\*IP  
ADDRESS : 98.122.9.254/ [4]\*IP ADDRESS MASK : 255.0.0.0/ 4  
、 STATI ROUTES 6.18.4.5 ( STATIC ROUTES ) ENTRY  
NUMBER : 1/ [1]\*IP NETWORK/SUBNET : 20.4.28.0/ [1]\*IP  
ADDRESS MASK : 255.255.255.0/ [1]\*NEXT HOP : 20.1.254.8/  
ENTRY NUMBER : 2/ [2]\*IP NETWORK/SUBNET  
: 20.59.138.0 [2]\*IP ADDRESS MASK : 255.255.255.0 [2]\*NEXT  
HOP : 20.28.254.31 ENTRY NUMBER : 3/ [3]\*IP  
NETWORK/SUBNET : 20.59.149.0/ [3]\*IP ADDRESS MASK  
: 255.255.255.0/ [3]\*NEXT HOP : 20.58.254.9/ ENTRY  
NUMBER : 4/ [4]\*IP NETWORK/SUBNET : 20.59.148.0/ [4]\*IP  
ADDRESS MASK : 255.255.255.0/ [4]\*NEXT HOP

: 20.58.254.11/ ENTRY NUMBER : 5/ [5]\*IP  
NETWORK/SUBNET : 20.59.147.0/ [5]\*IP ADDRESS MASK  
: 255.255.255.0 [5]\*NEXT HOP : 20.58.254.13/ ENTRY  
NUMBER : 6/ [6]\*IP NETWORK/SUBNET : 20.59.146.0/ [6]\*IP  
ADDRESS MASK : 255.255.255.0/ [6]\*NEXT HOP  
: 20.58.254.15/ ENTRY NUMBER : 7/ [7]\*IP  
NETWORK/SUBNET : 20.59.145.0/ [7]\*IP ADDRESS MASK  
: 255.255.255.0/ [7]\*NEXT HOP : 20.58.254.17 ENTRY  
NUMBER : 8/ [8]\*IP NETWORK/SUBNET : 20.59.144.0/ [8]\*IP  
ADDRESS MASK : 255.255.255.0/ [8]\*NEXT HOP  
: 20.58.254.19/ ENTRY NUMBER : 9/ [9]\*IP  
NETWORK/SUBNET : 20.59.143.0/ [9]\*IP ADDRESS MASK  
: 255.255.255.0/ [9]\*NEXT HOP : 20.58.254.21/ ENTRY  
NUMBER : 10/ [10]\*IP NETWORK/SUBNET : 20.59.142.0/  
[10]\*IP ADDRESS MASK : 255.255.255.0/ [10]\*NEXT HOP  
: 20.58.254.23/ ENTRY NUMBER : 11/ [11]\*IP  
NETWORK/SUBNET : 20.59.141.0/ [11]\*IP ADDRESS MASK  
: 255.255.255.0/ [11]\*NEXT HOP : 20.58.254.25/ ENTRY  
NUMBER : 12/ [12]\*IP NETWORK/SUBNET : 20.59.140.0/  
[12]\*IP ADDRESS MASK : 255.255.255.0/ [12]\*NEXT HOP  
: 20.58.254.27/ ENTRY NUMBER : 13/ [13]\*IP  
NETWORK/SUBNET : 20.59.139.0/ [13]\*IP ADDRESS MASK  
: 255.255.255.0/ [13]\*NEXT HOP : 20.58.254.29/ ENTRY  
NUMBER : 14/ [14]\*IP NETWORK/SUBNET : 20.59.137.0/  
[14]\*IP ADDRESS MASK : 255.255.255.0/ [14]\*NEXT HOP  
: 20.58.254.33/ ENTRY NUMBER : 15/ [15]\*IP

NETWORK/SUBNET : 20.59.250.0/ [15]\*IP ADDRESS MASK  
: 255.255.255.0/ [15]\*NEXT HOP : 20.58.254.7/ ENTRY  
NUMBER : 16/ [16]\*IP NETWORK/SUBNET : 20.59.136.0/  
[16]\*IP ADDRESS MASK : 255.255.255.0/ [16]\*NEXT HOP  
: 20.58.254.16/ (T002) 100Test 下载频道开通，各类考试题目直  
接下载。详细请访问 [www.100test.com](http://www.100test.com)