

CISCO3640配QOS承诺访问速度(CAR) PDF转换可能丢失图片或格式，建议阅读原文

https://www.100test.com/kao_ti2020/267/2021_2022_CISCO3640_E9_c101_267018.htm 只包括承诺访问速度（CAR）这部份配置.....3640#show run

```
Current configuration:!  
version 12.0  
service timestamps debug uptime  
service timestamps log uptime  
no service password-encryption!  
hostname Router!  
!  
ip subnet-zero!!!!  
interface Ethernet0/0  
no ip address  
no ip directed-broadcast  
shutdown!  
interface Serial0/0  
no ip address  
no ip directed-broadcast  
no ip mroute-cache  
shutdown  
no fair-queue!  
interface Serial0/1  
no ip address  
no ip directed-broadcast  
shutdown!  
interface Serial1/0  
no ip address  
no ip directed-broadcast  
shutdown!  
interface Serial1/1  
no ip address  
no ip directed-broadcast  
rate-limit output access-group 101 128000 24000 32000 conform-action set-prec-transmit 3 exceed-action set-prec-transmit 0  
rate-limit output access-group 102 16000 8000 9000 conform-action set-prec-transmit 2 exceed-action 0 drop  
rate-limit output access-group rate-limit 1 32000 8000 12000 conform-action transmit exceed-action transmit  
rate-limit output 48000 8000 10000 conform-action set-prec-transmit 0 exceed-action 0 drop  
shutdown!  
interface Serial1/2  
no ip address  
no ip directed-broadcast  
shutdown!  
interface Serial1/3  
no ip address  
no ip directed-broadcast  
shutdown!  
interface Serial3/0  
no ip address  
no ip directed-broadcast  
shutdown!  
interface Serial3/1  
no ip address  
no ip address  
no ip directed-broadcast  
shutdown!  
interface Serial3/3  
no ip address  
no ip directed-broadcast  
shutdown!  
ip classless  
no ip http
```

```
server!access-list 101 permit tcp any any eq wwwaccess-list 102
permit tcp any any eq smtpaccess-list rate-limit 1 5!line con
0transport input noneline aux 0line vty 0 4!end3640# 100Test 下载
频道开通，各类考试题目直接下载。详细请访问
www.100test.com
```