

查看Linux系统版本主要采用哪些方法 PDF转换可能丢失图片或格式，建议阅读原文

[https://www.100test.com/kao\\_ti2020/181/2021\\_2022\\_\\_E6\\_9F\\_A5\\_E7\\_9C\\_8BLinu\\_c103\\_181712.htm](https://www.100test.com/kao_ti2020/181/2021_2022__E6_9F_A5_E7_9C_8BLinu_c103_181712.htm) 1) 登录到服务器执行

`lsb_release -a`，即可列出所有版本信息，例如：

```
[root@3.5.5Biz-46 ~]# lsb_release -a
LSB Version: 1.3 Distributor
ID: RedHatEnterpriseAS Description: Red Hat Enterprise Linux AS
release 4 (Nahant Update 1) Release: 4 Codename: NahantUpdate1
```

[root@3.5.5Biz-46 ~]# 这个命令适用于所有的linux，包

括Redhat、SuSE、Debian等发行版。2) 登录到linux执行`cat`

`/etc/redhat-release`，例如如下：`[root@3.5.5Biz-46 ~]# cat`

```
/etc/redhat-release
Red Hat Enterprise Linux AS release 4 (Nahant
Update 1) [root@3.5.5Biz-46 ~]# 这种方式下可以直接看到具体的
```

版本号，比如 AS4 Update 1 3) 登录到linux执行`rpm -q`

`redhat-release`，例如如下 `[root@3.5.5Biz-46 ~]# rpm -q`

```
redhat-release
redhat-release-4AS-2.4 [root@3.5.5Biz-46 ~]# 这种方式下可看到一个所谓的release号，比如上边的例子是2.4 这个release号和实际的版本之间存在一定的对应关系，如下：
```

```
redhat-release-3AS-1 -> Redhat Enterprise Linux AS 3
```

```
redhat-release-3AS-7.4 -> Redhat Enterprise Linux AS 3 Update 4
```

```
redhat-release-4AS-2 -> Redhat Enterprise Linux AS 4
```

```
redhat-release-4AS-2.4 -> Redhat Enterprise Linux AS 4 Update 1
```

```
redhat-release-4AS-3 -> Redhat Enterprise Linux AS 4 Update 2
```

```
redhat-release-4AS-4.1 -> Redhat Enterprise Linux AS 4 Update 3
```

```
redhat-release-4AS-5.5 -> Redhat Enterprise Linux AS 4 Update 4
```

注意：第(2)(3)两种方法只对Redhat Linux有效 100Test 下载频

道开通，各类考试题目直接下载。详细请访问

[www.100test.com](http://www.100test.com)