

工大CCNP拓扑修改版Dynamips拓扑配置(下)Cisco认证考试  
PDF转换可能丢失图片或格式，建议阅读原文

[https://www.100test.com/kao\\_ti2020/581/2021\\_2022\\_\\_E5\\_B7\\_A5\\_](https://www.100test.com/kao_ti2020/581/2021_2022__E5_B7_A5_E5_A4_A7CCNP_c101_581412.htm)

[E5\\_A4\\_A7CCNP\\_c101\\_581412.htm](https://www.100test.com/kao_ti2020/581/2021_2022__E5_B7_A5_E5_A4_A7CCNP_c101_581412.htm) [[router R5]] image =  
D:dy6pre2npsdynamipsunzip-c3620-i-mz.122-37.bin model = 3620  
console = 3005 ram = 32 confreg = 0x2142 idlepc = 0x6036ce68  
exec\_area = 32 mmap = true slot0=NM-4E slot1 = PA-4T f0/0 =  
SW1 17 f0/1 = SW1 18 f0/2 = SW1 19 f0/3 = SW1 20 s1/1 = R6 s1/0  
s1/2 = FR1 5 [[router R6]] image =

D:dy6pre2npsdynamipsunzip-c3620-i-mz.122-37.bin model = 3620  
console = 3006 ram = 32 confreg = 0x2142 idlepc = 0x6036ce68  
exec\_area = 32 mmap = true slot0=NM-4E slot1 = PA-4T f0/0 =  
SW1 21 f0/1 = SW1 22 f0/2 = SW1 23 f0/3 = SW1 24 s1/1 = R7 s1/0  
s1/2 = FR1 6 [[router R7]] image =

D:dy6pre2npsdynamipsunzip-c3620-i-mz.122-37.bin model = 3620  
console = 3007 ram = 32 confreg = 0x2142 idlepc = 0x6036ce68  
exec\_area = 32 mmap = true slot0=NM-4E slot1 = PA-4T f0/0 =  
SW1 25 s1/1 = R8 s1/0 s1/2 = FR1 7 100Test 下载频道开通，各类  
考试题目直接下载。详细请访问 [www.100test.com](http://www.100test.com)